

Windows 10 Beginner/Refresher Course 2020

Session One: Navigating Windows 10

- **Caution:** If anyone is unfamiliar with using Windows at all, or the how to use a Mouse or keyboard they should first read Basic Lessons labeled Lesson 1 and Lesson 2 before these Windows 10 Sessions.
- **Introduction:** Windows 10 has lots of options and customizations we will try to discuss during the four sessions.
- Windows 10 wants to sign in with an online Microsoft Account and asks during setup.
 - If you have a Microsoft or Windows Live account, you can use it.
 - If you do not have one, Setup walks you through creating the Microsoft Account.
 - If you do not want a Microsoft Account, or wish not to use it for sign in:
 - Don't sign in with one or create one.
- Caveat to using Microsoft Account during setup:
 - If, on setup you use your Microsoft Account, the Username folder created will be the first 5 letters of your Account ID (**which may be to your disliking**).
 - Mine for example using jfdupre@comcast.net as the account would be **jfdup**.
 - **If you want to choose your User folder name, such as Jim, sign in during setup as a Local account, and switch to a Microsoft account later.**
 - You can now add free Apps from the Store with only a local account.
 - To purchase Apps from the Windows 10 Store will need a Microsoft Account.
- Microsoft account vs. Local account:
 - If you sign in with your Microsoft account:
 - Microsoft saves settings to use across additional devices.
 - Microsoft establishes an online storage called OneDrive.
 - You will not need to sign in to download and install purchased Apps from the Microsoft Store.
 - Otherwise, with both accounts the computer is managed and programs work the same.
- During setup, unless you have serious privacy concerns, for expediency of Setup
 - Just choose the recommended options.
 - Change privacy settings later if desired.
- Windows 10, after a few early questions, installs without much assistance needed.
 - If you have speakers and a microphone, much of the setup can be done by voice.
 - Windows 10 walks you through setting up the language, location, time zone, account, connecting to the Internet, and getting any necessary updates.
- Once setup completes you are presented with the Lock Screen.
 - To get the password box (Log on screen), touch a key, or swipe the touchscreen.
 - It is here you need to insert your password, if one was created.
 - If present, more common with laptops or tablets.
 - Windows 10 does offer other ways to sign in, such as using a PIN
 - Windows has many other Sign-in options depending on your hardware.
 - Check them in Settings: Start | Settings | Accounts | Sign in options.

Windows 10 Beginner/Refresher Course 2020

Session One: Navigating Windows 10

New Windows Features


- The important thing to note is **Windows Desktop itself has not changed.**
 - Manipulate and arrange just like always.
- Windows 10 introduces new Menu buttons
 - The **Ellipsis** menu  appears as 3 horizontal dots.
 - In other programs it may appear as 3 vertical dots.
 - The **Hamburger** menu comprises 3 short stacked horizontal lines  which look like a hamburger.
 - Both indicate the presence of (and clicking on) opens **More** options or information.
- Microsoft Edge
 - Microsoft developed a new streamlined and faster Browser with which to view the Internet.
 - We will speak more to this in our Session Two.
- Cortana
 - Microsoft's offering of a Personal Assistant.
 - Cortana can use your microphone or keyboard for entries.
 - Cortana can search, update an event in your Calendar app, open applications, send emails, and do searches, just for a few tasks to mention.
 - Just ask Cortana what she can do for a list or help.
- Mail App is provided to replace Outlook Express, Windows Mail and Windows Live Mail.
 - It is a satisfactory Email client for most functions.
 - Easy to set up most email accounts.
 - All you need is your email address and your email password.
 - Mail allows setup of multiple accounts.
 - Major drawback: Mail's contact list, the People App lacks the formal ability to create Mailing Groups.
 - Mail App is however the only Mail client Windows modern Apps recognizes.
 - Inter-related with the People App, Calendar App, and downloadable To Do App.
- Tips App
 - A helpful way to get familiar with many of the Windows 10 functions.
 - Find it in the Start menu App list.
 - Add a Desktop icon by dragging the icon from the list to the Desktop.
 - Don't worry, you are not removing it from the Apps list, only placing a shortcut.
 - For the Apps list, there is **no Send to Desktop as shortcut** right-click menu command.
- Tablet Mode
 - Switches Windows Desktop to a Tiles-only appearance for easier touch surface use.
- Action center became the Notifications icon at the far right of the Taskbar.
 - This is composed of an upper notification list, and lower Quick Action section.
 - Control what appears in the Quick Access at: Start | Settings | System | Notification and Actions | Edit your quick actions
 - This Quick Actions area offers access to many functional and appearance changes.
 - Clicking on one of the squares **toggles** items on and off.

Windows 10 Beginner/Refresher Course 2020

Session One: Navigating Windows 10

Windows 10 Desktop

- The Desktop itself and the way to manipulate and customize it really hasn't changed.
- Personalize Windows 10 using the Settings section Personalization.
 - Or access it with a right-click on the Desktop and choose Personalize.
 - Just like Windows 7.
 - Windows 10 just has more options.
- Besides for the usual ability to select windows title bar colors and backgrounds,
 - Windows 10 offers 2 overall color modes, Light and Dark.
 - The light theme keeps window backgrounds light with dark text.
 - The Dark color mode makes all the backgrounds black with light text.
- Windows 10 still offers Themes to control background pictures, title bars and taskbar.
 - It looks slightly different but functions the same.
 - The Theme may not change automatically on installation.
 - Once installed, you may have to return to Settings to select the new theme.
- From the Settings | Personalization window you can also choose what appears on the Lock screen.
- The only other difference is now with the Windows 10 Settings, areas to change are separated but available to pick from in the left column of the Settings page.



Windows 10 Beginner/Refresher Course 2020

Session One: Navigating Windows 10

Windows 10 Taskbar


- Just like all previous versions of Windows, there is a Taskbar of icons.
 - Initially, the Taskbar appears at the bottom of the screen, below the Desktop (background).
 - It can be moved to the top or sides as previously by dragging (if unlocked).
 - Change the Taskbar location also in Settings | Personalization | Taskbar.
- The Start button is still at the far left.
- Windows 10 introduced some new icons to the right of the Start button but before any shortcuts.
 - The magnifying glass icon  and search box offers a Search of computer and Internet.
 - This searches the computer and the Internet for applications installed, files on the computer, and Internet information.
 - A round circle icon  elicits Cortana, your Windows 10 Personal Assistant.
 - What looks like a movie-film icon  brings up the Task View.
 - Do not confuse this with Task Manager.
 - Task View is a whole new concept we will discuss later in Session Three.
 - Hide or display the new icons with a right-click on the icon.
 - Click to toggle check mark present (show) or absent (no show).
 - The Search box can be displayed only as an icon or hidden entirely.
- Windows 10 also introduces new icons in the Notification Area (far right-side icon grouping).
 - A People icon.
 - An on-screen keyboard icon.
 - A Windows Ink Workspace icon if you have a touchscreen on which to draw.
 - A new Internet Access icon replacing the Network icon when no Internet available.
 - It has the usual monitor screen for a wired network connection.
 - Wireless network connections display the quarter-circle lines.
 - New: If no Internet access, it changes to a World globe.
 - Hide or display the new icons with a right-click on the icon.
 - Click to toggle check mark present (show) or absent (no show).
- Adding shortcut icons to the taskbar is done easily:
 - In the Start menu, right-click on the item desired and hover over **More** to display the option to **Pin to the Taskbar**.
 - Or find the item in the Start menu and just drag it to the Taskbar.
 - Drag icons to the order you want, **the first 10 are accessed with Win + 1 – 0**.
- Removing any shortcut icon is removed by a right-click and **Unpin** the icon.
- Toolbars can be added to the Taskbar as always.
 - Right-click a blank area on the Taskbar and choose Toolbars | New Toolbar.
 - If no blank area (all icons across), right-click over the up-directed caret.
 - Navigate to the folder you wish available as a menu from the Taskbar.

Windows 10 Beginner/Refresher Course 2020

Session One: Navigating Windows 10

Windows 10 Start Menu

- This is the change in Windows 10 which frightens everyone.
 - Windows 10 returned to **modified** convention after a horrible Windows 8.
- But it really works the same as all previous start menus, just looks different.
 - It really works easier once you get past the new appearance.
- The Start menu has three sections versus the two on earlier Windows 10 versions.
 - There is a far-left narrow column of icons outlined in red for demonstration purposes.
 - The next column to the right is a list containing all the Apps and applications (Programs) installed on your computer outlined for demonstration in yellow.
 - Scroll the list to look for an item.
 - Note the alphabetical letters. Click on one to select another to jump to that area.
 - Then farther right is a larger area of squares called **Tiles** and is outlined for demonstration in black.
 - These Tiles also represent Programs or Apps installed.
 - However, you get to decide which items are represented.



- This Tile area, when introduced in Windows 8 as the entire Start screen replacing the traditional Start menu is what shook every long-time Windows user.
 - If it frightens you, don't use it.
 - **Ignore it or remove all the all the Tiles.**
 - Instead, customize it to replace those items missing from the old Start menu.
 - Just add Control Panel, or Devices and Printers, or similar.
 - Or add critical Apps or Programs you do not want to scroll for each time.
- The Start button also has a right-click menu.
 - This menu contains many items people often seek.
 - Quickly open the **Run** box, about **System** info, open **Device Manager**, **Task Manager**, **File Explorer**, or access **Settings**.
 - It offers many other options to accomplish various administrative feats.
 - Access this menu also with Windows logo key plus the letter "x".
- If you truly want the old Windows 7 start menu back, download either:
 - Classic Shell for free at: <http://www.classicshell.net/>
 - Start 10 Trial Buy it for \$5. <https://www.stardock.com/products/start10/>
 - I do not recommend doing this unless you absolutely cannot handle the new menu.
 - You lose many advantages the Windows 10 menu has to offer.
 - Such as the Start button right-click menu.
 - Quick access to all installed applications and any often-used folders.

Windows 10 Beginner/Refresher Course 2020

Session One: Navigating Windows 10

Windows 10 Start Menu (cont'd)

- Think of the far left Start menu column as the Control column, or Power column.
 - In the latest release, hovering over this column will expand it to reveal the names of each icon.
 - To expand this column if displaying only icons, click on the hamburger menu at the very top.
 - In this column, the bottom-most icon is the **Power** icon .
 - It offers the Shutdown, Restart, and Sleep options.
 - Just above is the **Settings** icon .
 - Microsoft is trying to replace the old Control Panel with a more modern approach familiar to tablets and smart phones.
 - But Control Panel is still available if you prefer it.
 - Click on Start and begin typing "control panel."
 - It appears at the top of the search column which opens.
 - If desired, right-click on it and Pin to Start.
 - Instead of a single window containing numerous options to consider by clicking boxes or radio buttons, each item is now separate and controlled by turning on or off.
 - Here you can change or add accounts, uninstall Apps and applications, personalize (customize) Windows, control Network connections, manually Update Windows 10, and much more.
 - The uppermost icon, not the very top of the column but top of the lower group, is the User Account icon .
 - This icon is where to go to Switch users, sign off, or lock the screen (assuming again you have set up a password).
 - Settings | Personalization | Start | **Choose which icons appear on Start** can add or remove additional icons for this column.
- The App list occupies the middle column of the Start menu.
 - This list includes all installed programs, applications, and modern Windows 10 Apps.
 - The list can be scrolled with the Mouse wheel,
 - A right-sided scroll bar.
 - **By default, many Windows scroll bars collapse to a thin line until the Mouse pointer is brought over them.**
 - Change collapse at Settings | Ease of Access | Scroll down the page to **Automatically hide scroll bars in Windows** and turn it Off.
 - Or jump from place to place using the Alphabet letters.
 - Use it to Pin desired applications to the Start Menu (right-side Tile pane)
 - Pin applications to the Taskbar
 - Right-click the application and hover over More to display the menu from which to choose **Pin to Taskbar**.

Windows 10 Beginner/Refresher Course 2020

Session One: Navigating Windows 10

Windows 10 Start Menu (cont'd)




- The Tile area (referred to as **pane**) is at the farthest right.
 - Several Microsoft-provided Tiles present with live changing information.
 - When connected to the Internet they display current information.
 - Such as News, stock info, weather, etc.
 - Individual Tiles can be moved, added or removed easily.
 - **Pin to Start** from the Start menu App list.
 - **When a Tile is pinned, it initially appears at the bottom** (or bottom right).
 - So it needs to be moved (drag) to the desired group or location.
 - **Unpin** with a simple right-click on the Tile.
 - Move an individual Tile by dragging it to the new location or group.
 - Whole groups of Tiles can be given a name, moved, or removed.
 - Name a group by clicking just above the Group and type or edit a name.
 - Move a group by dragging from the Title area (name) just above each Tile group.
 - **Unpin a group** by right-clicking the Group Name.
 - Create a new group by dragging a Tile to just above or just below the last group displayed.
 - A new pale thick line appears.
 - Drop the Tile just above (or below) this line to create the new Group.
 - Tiles can be resized.
 - Tiles can be an large elongated rectangle, a medium square, or a small square.
- The entire Tile pane can be made larger by dragging sides, top or corners.
 - To change, you must drag far enough to fit an entire group (3 or 4 medium squares).
 - Otherwise it snaps back to the original size.
- By default, each group contains 3 medium-sized Tiles across.
 - Change this to 4 across under Personalization settings
Start | Settings | Personalization | Start.
 - Turn on "**Show more Tiles on Start**".



Windows 10 Beginner/Refresher Course 2020

Session One: Navigating Windows 10

Other Windows 10 Features to be aware of:



- Windows 10 can sync settings, backgrounds, and Task View History between devices.
 - This is the purpose of Windows 10 wanting sign-in using an online presence.
 - It stores the information in OneDrive.
- File Explorer is the new name for Windows Explorer.
 - This is accessed by the manila folder icon on the Taskbar. 
 - Or any time you open any folder destination.
 - When it opens, by default it opens to the **Quick Access menu**.
 - You may prefer it open with **This PC**, the new name for (My) Computer.
 - To change it, open File Explorer and select the View ribbon (tab).
 - At the far right is an Options button and drop down. 
 - Click on Options button, then the top item is **Open File Explorer to:**
 - **Explorer to:**
 - In the drop-down list choose **This PC**. 
 - Now File Explorer will open displaying the main folders of Documents, Pictures, etc.
 - And just below the main User folders displays the drives attached or installed on the computer (such as a DVD drive or USB drive).
 - The File Explorer window works just like Windows Explorer, except with a ribbon interface to display many of the file management tasks rather than menu driven.
 - File Explorer has 2 panes.
 - The left pane is the folder pane just like Windows 7, but adds:
 - Quick Access folders (pinned) and OneDrive folders.
 - Adding to Quick Access is just like Windows 7.
 - Navigate to the desired folder then right-click on Quick Access.
 - Pin the current folder to Quick access.
 - Just like 7, when a folder is selected in the left column, its entire contents is displayed in the pane on the right side. 
 - All the same keyboard shortcuts and right-clicks work the same.
 - File Explorer still has the **search box** in the upper right-hand corner to search the contents of the displayed folder.
- Personalize Windows 10 using the Settings section Personalization.
 - Or access it with a right-click on the Desktop and choose Personalize.
 - Just like Windows 7.
 - Windows 10 just has more options.

Windows 10 Beginner/Refresher Course 2020

Session One: Navigating Windows 10

Other Windows 10 Features to be aware of:

- Inserting an external drive or a CD/DVD displays a pop-up in the lower right corner.
 - The only difference, the pop-up appears for only a few short seconds.
 - Once it disappears, you need to open File Explorer in order to access the drive.
 - This pop-up if clicked displays options shown at right for the specific device much like Windows 7.



- Microsoft Edge
- Windows 10 Mail app
- Microsoft Store
- For power users, the Command Prompt is replaced by PowerShell.
 - PowerShell allows copy and paste unlike Command prompt.

Windows 7 Features absent from Windows 10

- Windows 10 no longer include a program or app to play video DVDs.
 - Windows Media Player is still included but handles only Audio.
 - Need to install a DVD viewer program download, or App from Microsoft Store.
 - Such as VLC Player or similar.
 - Downloaded program works better than Windows Store App.
- Windows 10 no longer creates video discs.
 - Windows Movie Maker and Windows DVD writer are gone.
 - Requires a free download or paid-for application.
 - Such as Adobe Premiere, or a free program download.
- Windows 10 DOES still write to DVD and CD media for data discs.
 - Windows Media Player still Rips and Creates Audio discs.

Windows 10 Features that are unchanged

- Manipulating windows and files/folders
 - Resizing, moving, Cut, Copy, and Paste
 - Creating new folders, renaming, deleting, Cut, Copy, and Paste, etc.
- Installation of programs (applications)