

Windows 10 Features 2016

Introductory Remarks

- With Windows 10, Microsoft returns Windows desktop to us.
- Windows 10 combines the best features of both Windows 7 and 8, but makes them both better by adding features to each.
 - Searching for programs, apps, and files is easier.
 - Just open Start, and begin typing.
 - Searches files, web, settings, and Windows help.
- Whether it be an App, or a traditional program, they now all open the same, **as windows on the desktop**, fully resizable windows.
 - Use them full screen, or any size.
 - Snap as many as four to a screen.
 - Open as many as you want.
- Yes, Windows 10 has changed its appearance.
 - Some claim to like it.
 - Some claim to dislike it.
 - But I do not know anyone who has stayed more than a week with it that does not like it.
 - It is still relatively new, and there are rough spots, like all new OS.
- New to Windows 10 are more universal modern menu icons.
 - "**Hamburger**" Menus (three horizontal lines look like a hamburger and bun).
 - **Ellipsis** (...) menus indicate "there is more to see".
 - Used to denote more items are available, or more "path" hidden.
- Updating to Windows 10 keeps most of your installed programs, apps, and data.
 - Unless you choose a fresh install.
- Windows 10 upgrade is free until July 29, 2016!
 - Except for Windows XP and Vista.
 - Not free to upgrade to Windows 10
 - AND require a fresh install.
 - Meaning you must reinstall all programs and devices.
- End of 2015, Microsoft released the first "big" update.
 - Focused on fixing bugs and improving current features with this update which previously would have amounted to a "first Service Pack".
- A second major update is scheduled for mid-2016 and is promised to add new features to Edge, Mail, etc.
- Yes, Windows 10 places a lot of Privacy on the Internet.
 - Check out the article on our website [Regain Windows 10 Privacy](#).

Windows 10 Features 2016

Windows 10 Features

Start Menu

- Windows 10 again has a Start menu.
 - Use it like any other Windows version,
 - Or make it full screen like Windows 8 by Personalizing.
 - Go to Start, Settings, and open Personalization (not from Control Panel, as it opens only themes)
 - Or Right-click an empty screen area and choose Personalize.
- The Windows 10 Start menu looks a little different.
 - On the left, are links to Frequently used programs at the top, and a few important functions at the bottom, including **All Apps**.
 - **Settings**, which offers many configuration changes without using the Control Panel.
 - Is set to mimic smartphone configuration methods.
- Don't be confused, **All Apps includes** (replaces All Programs) both modern apps introduced with Windows 8 as well as all the traditional programs (Applications).
- Windows 10 in the Start menu All Apps offers a **Get Started App**.
 - Explains many Windows 10 functions and configuration capabilities.
 - Pin the Get Started to the taskbar or drag it to the desktop.
- Customizing the Start menu is easy.
- Drag apps and applications from the All Apps list to the right pane (side) of the Start menu, the Desktop, or the Taskbar.
- Right-click on the Start menu to display the **Quick Access menu**.
 - Quick access to Programs and Features, Run box, Device Manager, Task Manager, and Control Panel to name just a few.
 - Or to Shutdown (Restart, Sleep, Hibernate, or Sign Out).
- Switch users by clicking on the User Name top left pane.
 - This does no longer display User folders.
 - Add User folders to the Start menu under Start | Settings | Personalization | Start.

Windows 10 Features 2016

Taskbar

- Taskbar is just the same as Windows 7, but with new icons added.
 - Cortana or Search box
 - Task View
 - Displays thumbnails of all open windows.
 - Also provides opportunity to add "**Virtual Desktops**".
 - Have a productivity desktop and a separate entertainment or game desktop.
 - Microsoft Edge
 - New browser meant to replace Internet Explorer.
 - Store (links to the Windows Store to obtain more Apps).
 - **Store** (accesses the Microsoft Store to find and install free or paid for Apps).
 - Pin items by:
 - Right-click in the All Apps list and "pin to".
 - Drag to taskbar from All Apps list.
 - Action Center (talk bubble icon in the Notification area at the right).
 - Turns white when a new notification is available.
 - Bottom area contains access to other features (Connect to a device, and Bluetooth for example).
 - Windows 10 switches easily between Desktop and "**Tablet**" Modes.
 - Customize Notification area
 - Right-click taskbar and choose Properties.
 - Start|Settings|System|Notifications and Actions
 - Select which icons appear.
 - Turn System icons on or off.

Cortana

- Acts as a personal assistant.
 - Reacts to voice as well as typed commands.
 - Once the microphone (if present is configured (see below).
 - Provides help for Windows functions as well via Web.
 - Consider turning on "**Hey Cortana**", so all you need to do is say "Hey Cortana" to have the personal assistant listen for voice commands.
 - **Find what Cortana can do: Type "What can you do?"**

Windows 10 Features 2016

Microsoft Edge

- Microsoft Edge is the new streamlined Internet browser intended to replace Internet Explorer.
 - But Internet Explorer is still available should you prefer to use it.
 - You can also import your Favorites from Internet Explorer or another browser.
 - Display the **Favorites bar** if desired (by clicking the ellipsis menu|Settings|Favorite Settings and Turn on Favorites bar button.
 - Offers a **Reading view**.
 - Find Favorites, History, and Downloads with the “**Hub**” (the hamburger menu, top right).
 - Mark up by **writing** or **highlighting** items on a web page, then share that marked up webpage.
 - Also, Cortana can help when surfing the web. A blue Cortana icon appears in the browser bar (on the right) with "I've got more info," when Cortana can provide more information about the website (Such as Yelp info on a restaurant, such as Sneaky Pete's www.sneakypetesbonita.com).
- Open multiple instances of Edge:
 - Click on the ellipsis (...) menu and choose new window.
 - Right-click edge icon on the taskbar and choose Microsoft Edge.
 - This function was added by the recent update.
 - Or drag an existing tab downward.

File Explorer

- File Explorer is also now using the ribbon interface rather than menus.
 - New Folder is on the Home ribbon.
 - Email link is on the Share ribbon.
- File Explorer window by default opens in the Quick Access view.
 - Open it in **This PC**, (the equivalent of My Computer) (like Windows7 & 8)
 - Open File Explorer and switch to the View ribbon.
 - On the View ribbon, click on Options (far right) and choose Change Folder and Search Options.
 - On the top of the General tab, change "Open File Explorer to" from Quick Access to This PC.
 - Apply and OK.

More on Virtual Desktops

- Purpose is to allow screens with specific open windows.
 - For example: One screen with windows (programs open) which are for completing work items
 - While a second desktop has windows open to play games, or entertainment.
- Open the Task View (button to the far left, but right of Cortana on Taskbar).
- Click on the New Desktop button (+ sign) in the lower right.
- Open any programs you want.
- To switch desktops, use the Task View button and choose the desired desktop.
- Drag programs from one desktop to another.
 - Drag a program until it reduces in size and drag onto the other desktop.

Windows 10 Features 2016

Noteworthy included Apps and those available at the Windows Store

- Included
 - Get Started
 - Photos
 - Calendar
 - Groove Music
 - Phone Companion helps connect smartphones to your computer.
- Available at the Store
 - Using the Windows Store requires a Microsoft Account
 - It is free.
 - Go to live.com to sign up, if not given an opportunity at the site you are at.
 - Word, Excel, and PowerPoint are all available as Mobile Apps for free.
 - They have limited functionality from the full programs, but sufficient for many.

Windows 10 Features 2016

- Set up Cortana
 - Click in the search box (left side Taskbar), and agree to the various request and Next boxes.
 - It will ask you what you want to be called.
 - Click on the microphone icon (**will only appear if you have a microphone**)
 - it may tell you your microphone isn't good caliber.
 - Just ignore that and continue with the microphone setup.
 - It will ask you to read a paragraph, then most likely will have a Finish button.
 - Now, a right-click on the Taskbar (empty area), will allow you to decide if Cortana is displayed as a search box, just an icon, or hidden from view altogether.
 - If you had a very full Taskbar of icons prior to an Upgrade, the Cortana search box may be hiding some.
 - In that case you need Cortana to display just as an icon.
 - More customization (turning functions and off) can be accomplished through the various menus found to the left under the "Hamburger menu".
 - Click on the hamburger menu to make the icons have labels.
 - Choose Notebook, and then Settings.
 - Consider turning on "**Hey Cortana**", so all you need to do is say "Hey Cortana" to have the personal assistant take commands.
 - Some are concerned with privacy with Hey Cortana. Is she listening to more than just your commands? Is she eavesdropping?
 - **Find what Cortana can do: Type "What can you do?"**

Windows 10 Features 2016

- Set up Microsoft Edge, a new streamlined browser replaces Internet Explorer.
 - You can also import your Favorites from Internet Explorer or Chrome.
 - Open Edge Settings by clicking on the ellipsis (...) menu and choosing Settings at the bottom of the list, then **Favorite settings**.
 - Click on the "Import favorites from another browser" link.
 - Choose IE or Chrome, etc.)
 - Turn on the **Favorites bar** if desired (by clicking the button.
 - Put a **home button** on the Navigation bar.
 - On the Settings list, scroll to the bottom and use the "View advanced settings button, and turn on "Show the home button".
 - Change (or Add) a home page.
 - By default, Edge opens with the "about:start page.
 - Change the radio button to the "A specific page or pages".
 - Choose Custom from the drop-down list.
 - By doing so, an " Enter a web address " box appears
 - In the "Enter a web address box, type the URL for the desired page.
 - It may be easier to first go to that page, and Copy the URL from the address line.
 - Once entered, be sure to click on the Plus sign (to the right of the box) to add it.
 - You can add as many pages as you want to open.
 - Remove pages by clicking the "X" to the right of the address.
 - **Also**, you can set a home page button, without the page opening at start, only when you click the Home button.
 - Restore Internet Explorer to the Start menu or Taskbar.
 - Some websites still require the java and active x functions to display content properly.
 - Edge will offer the opportunity to "Open this web page in Internet Explorer.
 - First find it by opening Cortana (the search box) or Start menu and typing Internet. Internet Explorer should appear at the top of the list. Right-click to Pin it, Start or Taskbar.
 - Restore Internet Explorer as the default browser if desired by:
- Return Internet Explorer as the default web browser (replacing Microsoft Edge).
 - Going to Control Panel (right-click the Start button) and choosing Default programs, the select Internet Explorer and set as default.

Windows 10 Features 2016

- Further Customization of Microsoft Edge
 - Rearrange icons in the Favorites, or on the Favorite Bar
 - Open Microsoft Edge.
 - Icons will now drag back and forth (last Windows update)
 - Or...Open the Favorites list by clicking the "Hub" (three bars to the right of the star).
 - Pin it to the side.
 - Now you can drag items to the desired locations.
 - Unfortunately, Edge has not yet offered a way of simple alphabetizing yet.
 - Microsoft Edge, if not imported, stores the favorites in:
 - **%UserProfile%\AppData\Local\Packages\Microsoft.MicrosoftEdge_8wekyb3d8bbwe\AC\MicrosoftEdge\User\Default\Favorites**
 - Mine are not there; nor are the new ones put in User_Name's Favorite folder.
 - You may be warned by Norton or other antivirus programs that Edge is not currently capable of having "Extensions", which makes it less secure.
 - Just ignore the warning for now, or click the "Don't remind me about this again" link to the left of the warning.
 - Make Microsoft Edge search result open in new tab.
 - Perform a search, any search.
 - On the window, click the sprocket (upper right within the search window, not Title bar area) and choose Settings.
 - Within Settings go to the Web tab.
 - On the Web settings, put a check in "Open links in a new browser window".
 - Click Save (lower left).
 - Customize the about:start page weather
 - Click on the current location.
 - Search for your location or use location finder.
 - Set location as a favorite (star+ button).
 - Set as home location by clicking on "Make this place my home ".

Windows 10 Features 2016

More on Customizing the Start Menu and Taskbar

- Customize the Taskbar.
 - Right-click the Taskbar and choose Properties.
 - Navigation tab no longer applies to the Start button and appearance.
 - Still useful to customize which icons show in the Notification area. Offers link to the System Settings.
 - Can still Auto-hide, use small taskbar icons, lock, and change taskbar position.
- Customize the Desktop appearance.
 - Right-click the desktop and choose Personalize.
 - Then in the left column menu choose Background, Colors, Lock Screen, or Themes.
- Customize the Start menu.
 - Right-click the desktop screen, choose Personalize and then choose Start (in the menu on the left).
 - Choose which folders appear in the left-hand Start menu.
 - Start|Settings|Personalization|Start, then "Choose which folders appear on Start" (at the bottom).
 - Offerings limited to a select few folders.
 - Personal folder (User folders) is a good one to show.
 - However, you can also pin to the right side (with a right-click) ANY folder (such as Documents, Pictures, etc., or Control Panel) to the right-hand menu of tiles.
 - Or simply drag from All Apps view.
 - And create your own group by dragging an item top or bottom until a bar appears, then let go.
 - May need to use Cortana to find certain system folder components).
 - Unpin any unwanted Tile by right-clicking and choosing Unpin.
 - Organize the locations of tiles by dragging.
 - Drag groups around by grabbing the title bar of the group.
 - Create a new grouping by dragging to the top of the menu until a bar appears.
 - Name, or rename groups by clicking in the area just above a group.
 - Resize the Start menu by dragging an edge or corner (like a window).
 - Make it full screen by turning on in Personalize.

Windows 10 Features 2016

Select Windows keyboard shortcuts for Windows 10

- Most Windows keyboard shortcuts work for the last few versions of Windows.
- Win logo-Arrow keys
 - Win logo-Up arrow snaps window to maximized
 - Win logo-Down arrow restores window size if maximized, or minimizes window if window size.
 - Win logo-Left arrow snaps window to left.
 - Win logo-Right arrow snaps window to right.
- Win logo-E opens File Explorer.
- ALT key-Up arrow goes up one folder level while using File Explorer.
- Win logo-T cycles through Taskbar icons.
 - Enter then opens the task.
- Win logo-Print Screen (PRT SCN) key takes a screen shot and saves it to a folder within Pictures.
- Win logo-CTRL-D creates a new virtual desktop.
- Win logo-Tab shows all your desktops via Task View.
- Win logo-A opens the Action Center.
- Win logo-C opens Cortana ready to talk to her.
- Win logo-S opens Cortana.
- Win logo-I (i) opens Settings.
- Win logo-X opens the Start button right-click context menu.
- Win logo-TAB opens Task View (to switch apps; switch or create Virtual Desktops).
- Win logo-CTRL-D creates a new Virtual Desktop.
- Win logo-CTRL-F4 closes the current desktop.
- Win logo-CTRL-left or right arrow keys switches between Virtual desktops.
- Win logo-comma (,) hide open windows temporarily to see desktop.
- Win logo-L locks the PC (password then needed to reopen).
- ALT-F4 closes active window
 - If no windows active, brings up the Shutdown menu.
- Again, Win logo-Left arrow snaps window to left.
 - Win logo-Up arrow then snaps window to upper quadrant.
- Similarly, Win logo-Right arrow snaps window to right.
 - Win logo-Down arrow snaps window the lower quadrant.

Windows 10 Features 2016

Browser (Microsoft Edge) Shortcuts

- CTRL-T opens new tab.
- CTRL-D bookmark's page.
- CTRL-ENTER adds .com to end of a web address.
- CTRL-L highlights current URL in address bar
 - Similarly ALT-D does the same (previously an Internet Explorer shortcut).
- CTRL-TAB cycles through open tabs.
 - Similarly it also does o in Internet Explorer.

Find more Windows 10 information at: <http://windows.microsoft.com/en-us/windows-10/getstarted-get-to-know-microsoft-edge>